

GC Demand & Fueling on the Karoo

How to install, set up and unlock

During the ride, the app shows your **carbohydrate demand**: how much the ride is asking for, estimated from your power and your personal curve. It knows nothing about your food or drink, and it does not measure them.

You get one file: **GC-Demand-Fueling-Karoo-0.2.8.apk**.

How you install it depends on your Karoo model.

- **The new Karoo, released in 2024** (often called the Karoo 3): from your phone, no computer. Follow part A.
- **Karoo 2**: from a computer, with the USB cable. Follow part B.

Already have an earlier version on your Karoo? Install this one the same way, on top of it, without removing the old one: your numbers and your unlock stay there.

A. New Karoo (Karoo 3): from your phone

Before you start: the Karoo on Wi-Fi, and the **Hammerhead Companion** app on your phone, connected to this Karoo.

1. Get the app file on your phone (through WhatsApp, for example).
2. In WhatsApp, **press and hold** the file and choose **Share** (on an iPhone: tap the file, then the share button). Do not install it on the phone: the app is for the Karoo.
3. In the list, choose **Hammerhead Companion**. The phone shows that it is transferring.
4. The install screen appears on the Karoo. Tap **Install**.


B. Karoo 2: from a computer

You need: a computer (Windows or Mac), the Karoo's USB cable, and the **Karoo 2 Kit** file, which has the app and the installer.

1. **On the Karoo 2, turn on developer mode.** Open **Settings** → **About** and tap **Build Number** several times, until it says you are now a developer. Go back one screen, open **Developer Options** and turn on **USB debugging**.
2. **On the computer, download Google's tool** called **SDK Platform-Tools**, from the official Android site: **developer.android.com/tools/releases/platform-tools**. Unzip it. You get a folder called **platform-tools**.
3. **Put the kit inside that folder:** the app file and the installer (**instalar-no-karoo.bat** on Windows, **instalar-no-karoo.command** on a Mac).
4. **Connect the Karoo 2 to the computer with the cable** and double-click the installer. If the Karoo asks about "USB debugging", tick "always allow" and tap OK. The window ends with **PRONTO / DONE**.

After installing (both models)

1. **Open the app once:** on the Karoo, **Apps** → **GC Demand & Fueling**.
2. **Enter your numbers** and tap **Save**: weight, reference power (FTP) and 5-minute power. Use the numbers you got from GC. Below the button, the screen shows the curve they produce.
3. **Put the field on a page.** Open your ride profile, in **Data Pages** tap +, choose a data page and, in the list of fields, choose **Carb demand page** (the filter at the top of the list helps). It works best taking up the whole page.
4. **Ride with your power meter on.**



The page during a ride: the total, the power right now, the FEC (Functional Energy from Carbohydrate) demand, the demand right now, and each hour.

What the field tells you during the ride


Every now and then, and **without any beep**, the list on the page gives way to a message for 30 seconds, alternating with the data so the numbers never disappear:

1. **A suggested carbohydrate range per hour**, every 5 minutes — for example "30-60 g/h". It is a suggestion from the literature, **not a prescription**, and it is never above what your ride is asking for.
2. **At 2 minutes**, once, the numbers the app is working with: your FTP and your weight. If either is wrong, this is where you see it — a wrong FTP makes every other number wrong without looking wrong.
3. **Every half hour**, a reminder that the demand you do not replace comes out of your glycogen.
4. **Above FTP**, after a full minute, a note that this pace does not last an hour. And the "FEC 100 in" line switches to your

W' reserve, as a percentage: above FTP, what runs out first is that reserve, not carbohydrate.

If you are **on another page** of the Karoo, the suggestion shows on top of it, also without sound. The two switches — **On-screen messages** and **Alert on other screens** — are on the app's screen and come turned on.

A third one, **W' reserve graph**, comes **turned off**. When on, it draws the last half hour of your W' reserve at the foot of the page: how much each attack spent and how much came back.



The suggestion, in place of the list, for 30 seconds.

The 7-day free trial and the unlock code

The app works **free for 7 days**, counted from the first ride in which it counts (with your numbers saved and the power meter on). After that it asks for this Karoo's unlock code.

1. **Find this Karoo's code** at the top of the **Apps → GC Demand & Fueling** screen. It also shows on the carbohydrate page, before you start.
2. **Send that code** by WhatsApp to **+55 15 99107-5408**, through Instagram **@gregorycinto** or through the website

gccyclingnutrition.com.br. You get an unlock code back.

3. **Type the unlock code** in the **Unlock code** field, on the same screen, and tap **Save**. You will see **"Unlocked on this Karoo."** No internet needed.

This Karoo's code

Z3T2-A5KH

Free trial: 7 days. After that,
the app locks until it gets the
unlock code.

Unlock code

XXXX-XXXX

Free for 7 days from the first ride in
which the field counts. After that

The top of the settings screen: this Karoo's code, the free trial, and where to type the unlock code.

The app never locks in the middle of a ride. If the 7 days run out during a ride, it only locks when the ride ends. Each unlock code works on one Karoo only.

GC Demand & Fueling 0.2.8 for Hammerhead Karoo. For information only: it does not diagnose, treat or replace professional care.